Package 'parallelMap'

July 23, 2025

Title Unified Interface to Parallelization Back-Ends

License BSD_2_clause + file LICENSE

Version 1.5.1

Description Unified parallelization framework for multiple back-end, designed for internal package and interactive usage. The main operation is parallel mapping over lists. Supports 'local', 'multicore', 'mpi' and 'BatchJobs' mode. Allows tagging of the parallel operation with a level name that can be later selected by the user to switch on parallel execution for exactly this operation.

```
URL https://parallelmap.mlr-org.com,
      https://github.com/mlr-org/parallelMap
BugReports https://github.com/mlr-org/parallelMap/issues
Depends R (>= 3.0.0)
Imports BBmisc (>= 1.8), checkmate (>= 1.8.0), parallel, stats, utils
Suggests BatchJobs (>= 1.8), batchtools (>= 0.9.6), data.table, Rmpi,
      rpart, snow, testthat
ByteCompile yes
Encoding UTF-8
RoxygenNote 7.1.0
NeedsCompilation no
Author Bernd Bischl [cre, aut],
      Michel Lang [aut] (ORCID: <a href="https://orcid.org/0000-0001-9754-0393">https://orcid.org/0000-0001-9754-0393</a>),
      Patrick Schratz [aut] (ORCID: <a href="https://orcid.org/0000-0003-0748-6624">https://orcid.org/0000-0003-0748-6624</a>)
Maintainer Bernd Bischl <br/>
<br/>
dernd_bischl@gmx.net>
Repository CRAN
Date/Publication 2021-06-28 06:40:04 UTC
```

2 parallelExport

Contents

	parallelExport
	parallelGetOptions
	parallelGetRegisteredLevels
	parallelLapply
	parallelLibrary
	parallelMap
	parallelRegisterLevels
	parallelSource
	parallelStart
	parallelStop
T 3	1
Index	\mathbf{I}^{2}

parallelExport

Export R objects for parallelization.

Description

Makes sure that the objects are exported to slave process so that they can be used in a job function which is later run with parallelMap().

Usage

```
parallelExport(
    ...,
    objnames,
    master = TRUE,
    level = NA_character_,
    show.info = NA
)
```

Arguments

... character

Names of objects to export.

objnames (character(1))

Names of objects to export. Alternative way to pass arguments.

master (logical(1))

Really export to package environment on master for local and multicore mode? If you do not do this your objects might not get exported for the mapping func-

tion call. Only disable when you are really sure. Default is TRUE.

level (character(1))

If a (non-missing) level is specified in parallelStart(), the function only exports if the level specified here matches. See parallelMap(). Useful if this

function is used in a package. Default is NA.

parallelGetOptions 3

```
show.info (logical(1))
```

Verbose output on console? Can be used to override setting from options / parallelStart(). Default is NA which means no overriding.

Value

Nothing.

parallelGetOptions

Retrieve the configured package options.

Description

Returned are current and default settings, both as lists. The return value has slots elements settings and defaults, which are both lists of the same structure, named by option names.

A printer exists to display this object.

For details on the configuration procedure please read parallelStart() and https://github.com/mlr-org/parallelMap.

Usage

```
parallelGetOptions()
```

Value

ParallelMapOptions. See above.

parallelGetRegisteredLevels

Get registered parallelization levels for all currently loaded packages.

Description

With flatten = FALSE, a structured S3 object is returned. The S3 object only has one slot, which is called levels. This contains a named list. Each name refers to package from the call to parallelRegisterLevels(), while the entries are character vectors of the form "package.level". With flatten = TRUE, a simple character vector is returned that contains all concatenated entries of levels from above.

Usage

```
parallelGetRegisteredLevels(flatten = FALSE)
```

4 parallelLapply

Arguments

```
flatten (logical(1))
```

Flatten to character vector or not? See description. Default is FALSE.

Value

RegisteredLevels | character. See above.

parallelLapply

Parallel versions of apply-family functions.

Description

```
parallelLapply: A parallel lapply() version.
parallelSapply: A parallel sapply() version.
All functions are simple wrappers for parallelMap().
```

Usage

```
parallelLapply(xs, fun, ..., impute.error = NULL, level = NA_character_)

parallelSapply(
    xs,
    fun,
    ...,
    simplify = TRUE,
    use.names = TRUE,
    impute.error = NULL,
    level = NA_character_
)
```

Arguments

```
ХS
                  (vector | list)
                  fun is applied to the elements of this argument.
                  function
fun
                 Function to map over xs.
. . .
                 Further arguments passed to fun.
impute.error
                  (NULL | function(x))
                 See parallelMap().
level
                  (character(1))
                 See parallelMap().
simplify
                  (logical(1))
                 See sapply(). Default is TRUE.
use.names
                  (logical(1))
                 See sapply(). Default is TRUE.
```

parallelLibrary 5

Value

For parallelLapply a named list, for parallelSapply it depends on the return value of fun and the settings of simplify and use.names.

parallelLibrary

Load packages for parallelization.

Description

Makes sure that the packages are loaded in slave process so that they can be used in a job function which is later run with parallelMap().

For all modes, the packages are also (potentially) loaded on the master.

Usage

```
parallelLibrary(
    ...,
    packages,
    master = TRUE,
    level = NA_character_,
    show.info = NA
)
```

Arguments

... character

Names of packages to load.

packages (character(1))

Names of packages to load. Alternative way to pass arguments.

master (logical(1))

Load packages also on master for any mode? Default is TRUE.

level (character(1))

If a (non-missing) level is specified in parallelStart(), the function only loads the packages if the level specified here matches. See parallelMap().

Useful if this function is used in a package. Default is NA.

show.info (logical(1))

Verbose output on console? Can be used to override setting from options /

parallelStart(). Default is NA which means no overriding.

Value

Nothing.

6 parallelMap

parallelMap

Maps a function over lists or vectors in parallel.

Description

Uses the parallelization mode and the other options specified in parallelStart().

Libraries and source file can be initialized on slaves with parallelLibrary() and parallelSource().

Large objects can be separately exported via parallelExport(), they can be simply used under their exported name in slave body code.

Regarding error handling, see the argument impute.error.

Usage

```
parallelMap(
   fun,
   ...,
   more.args = list(),
   simplify = FALSE,
   use.names = FALSE,
   impute.error = NULL,
   level = NA_character_,
   show.info = NA
)
```

Arguments

fun function Function to map over Arguments to vectorize over (list or vector). more.args A list of other arguments passed to fun. Default is empty list. simplify (logical(1)) Should the result be simplified? See simplify2array. If TRUE, simplify2array(higher = TRUE) will be called on the result object. Default is FALSE. use.names (logical(1)) Should result be named? Use names if the first . . . argument has names, or if it is a character vector, use that character vector as the names. impute.error (NULL | function(x)) This argument can be used for improved error handling. NULL means that, if an exception is generated on one of the slaves, it is also thrown on the master.

This argument can be used for improved error handling. NULL means that, if an exception is generated on one of the slaves, it is also thrown on the master. Usually all slave jobs will have to terminate until this exception on the master can be thrown. If you pass a constant value or a function, all jobs are guaranteed to return a result object, without generating an exception on the master for slave

parallelRegisterLevels

errors. In case of an error, this is a simpleError() object containing the error message. If you passed a constant object, the error-objects will be substituted with this object. If you passed a function, it will be used to operate on these error-objects (it will ONLY be applied to the error results). For example, using identity would keep and return the simpleError-object, or function(x) 99 would impute a constant value (which could be achieved more easily by simply passing 99). Default is NULL.

level (character(1))

If a (non-missing) level is specified in parallelStart(), this call is only parallelized if the level specified here matches. Useful if this function is used in a

package. Default is NA.

show.info (logical(1))

Verbose output on console? Can be used to override setting from options /

parallelStart(). Default is NA which means no overriding.

Value

Result.

Examples

```
parallelStart()
parallelMap(identity, 1:2)
parallelStop()
```

parallelRegisterLevels

Register a parallelization level

Description

Package developers should call this function in their packages' base::.onLoad(). This enables the user to query available levels and bind parallelization to specific levels. This is especially helpful for nested calls to parallelMap(), e.g. where the inner call should be parallelized instead of the outer one.

To avoid name clashes, we encourage developers to always specify the argument package. This will prefix the specified levels with the string containing the package name, e.g. parallelRegisterLevels(package="foo", levels="dummy") will register the level "foo.dummy" and users can start parallelization for this level with parallelStart(<backend>, level = "parallelMap.dummy"). If you do not provide package, the level names will be associated with category "custom" and can there be later referred to with "custom.dummy".

Usage

```
parallelRegisterLevels(package = "custom", levels)
```

8 parallelSource

Arguments

package (character(1))

Name of your package. Default is "custom" (we are not in a package).

levels (character(1))

Available levels that are used in the parallelMap() operations of your package or code. If package is not missing, all levels will be prefixed with "package.".

Value

Nothing.

parallelSource

Source R files for parallelization.

Description

Makes sure that the files are sourced in slave process so that they can be used in a job function which is later run with parallelMap().

For all modes, the files are also (potentially) loaded on the master.

Usage

```
parallelSource(
    ...,
    files,
    master = TRUE,
    level = NA_character_,
    show.info = NA
)
```

Arguments

... character

File paths to sources.

files character

File paths to sources. Alternative way to pass arguments.

master (logical(1))

Source files also on master for any mode? Default is TRUE.

level (character(1))

If a (non-missing) level is specified in parallelStart(), the function only sources the files if the level specified here matches. See parallelMap(). Useful

if this function is used in a package. Default is NA.

show.info (logical(1))

Verbose output on console? Can be used to override setting from options /

parallelStart(). Default is NA which means no overriding.

parallelStart 9

Value

Nothing.

parallelStart

Parallelization setup for parallelMap.

Description

Defines the underlying parallelization mode for parallelMap(). Also allows to set a "level" of parallelization. Only calls to parallelMap() with a matching level are parallelized. The defaults of all settings are taken from your options, which you can also define in your R profile. For an introductory tutorial and information on the options configuration, please go to the project's github page at https://github.com/mlr-org/parallelMap.

Usage

```
parallelStart(
 mode,
  cpus,
  socket.hosts,
  bj.resources = list(),
  bt.resources = list(),
  logging,
  storagedir,
  level,
  load.balancing = FALSE,
  show.info,
  suppress.local.errors = FALSE,
  reproducible,
)
parallelStartLocal(show.info, suppress.local.errors = FALSE, ...)
parallelStartMulticore(
  cpus,
  logging,
  storagedir,
  level,
  load.balancing = FALSE,
  show.info,
  reproducible,
)
parallelStartSocket(
```

10 parallelStart

```
cpus,
  socket.hosts,
  logging,
  storagedir,
  level,
  load.balancing = FALSE,
  show.info,
  reproducible,
)
parallelStartMPI(
  cpus,
  logging,
  storagedir,
  level,
  load.balancing = FALSE,
  show.info,
  reproducible,
)
parallelStartBatchJobs(
 bj.resources = list(),
 logging,
  storagedir,
 level,
  show.info,
)
parallelStartBatchtools(
 bt.resources = list(),
  logging,
  storagedir,
  level,
  show.info,
)
```

Arguments

```
mode (character(1))
Which parallel mode should be used: "local", "multicore", "socket", "mpi",
"BatchJobs". Default is the option parallelMap.default.mode or, if not set,
"local" without parallel execution.

cpus (integer(1))
Number of used cpus. For local and BatchJobs mode this argument is ignored.
```

parallelStart 11

For socket mode, this is the number of processes spawned on localhost, if you want processes on multiple machines use socket.hosts. Default is the option parallelMap.default.cpus or, if not set, parallel::detectCores()

for multicore mode, max(1, [mpi.universe.size][Rmpi::mpi.universe.size] - 1)

for mpi mode and 1 for socket mode.

socket.hosts character

Only used in socket mode, otherwise ignored. Names of hosts where parallel processes are spawned. Default is the option parallelMap.default.socket.hosts, if this option exists.

bj.resources list

Resources like walltime for submitting jobs on HPC clusters via BatchJobs. See BatchJobs::submitJobs(). Defaults are taken from your BatchJobs config file.

bt.resources lis

storagedir

Analog to bj.resources. See batchtools::submitJobs().

logging (logical(1))

Should slave output be logged to files via sink() under the storagedir? Files are named <iteration_number>.log and put into unique subdirectories named parallelMap_log_<nr> for each subsequent parallelMap() operation. Previous logging directories are removed on parallelStart if logging is enabled. Logging is not supported for local mode, because you will see all output on the master and can also run stuff like traceback() in case of errors. Default is the option parallelMap.default.logging or, if not set, FALSE.

(character(1))

Existing directory where log files and intermediate objects for BatchJobs mode are stored. Note that all nodes must have write access to exactly this path. De-

fault is the current working directory.

level (character(1))

You can set this so only calls to parallelMap() that have exactly the same level are parallelized. Default is the option parallelMap.default.level or, if not set, NA which means all calls to parallelMap() are are potentially parallelized.

load.balancing (logical(1))

Enables load balancing for multicore, socket and mpi. Set this to TRUE if you have heterogeneous runtimes. Default is FALSE

show.info (logical(1))

Verbose output on console for all further package calls? Default is the option parallelMap.default.show.info or, if not set, TRUE.

suppress.local.errors

(logical(1))

Should reporting of error messages during function evaluations in local mode be suppressed? Default ist FALSE, i.e. every error message is shown.

reproducible (logical(1))

Should parallel jobs produce reproducible results when setting a seed? With this option, parallelMap() calls will be reproducible when using set.seed() with the default RNG kind. This is not the case by default when parallelizing in R,

12 parallelStop

since the default RNG kind "Mersenne-Twister" is not honored by parallel processes. Instead RNG kind "L'Ecuyer-CMRG" needs to be used to ensure parallel reproducibility. Default is the option parallelMap.default.reproducible or, if not set, TRUE.

... (any)

Optional parameters, for socket mode passed to parallel::makePSOCKcluster(), for mpi mode passed to parallel::makeCluster() and for multicore passed to parallel::mcmapply() (mc.preschedule (overwriting load.balancing), mc.set.seed, mc.silent and mc.cleanup are supported for multicore).

Details

Currently the following modes are supported, which internally dispatch the mapping operation to functions from different parallelization packages:

- local: No parallelization with mapply()
- multicore: Multicore execution on a single machine with parallel::mclapply().
- **socket**: Socket cluster on one or multiple machines with parallel::makePSOCKcluster() and parallel::clusterMap().
- **mpi**: Snow MPI cluster on one or multiple machines with parallel::makeCluster() and parallel::clusterMap().
- **BatchJobs**: Parallelization on batch queuing HPC clusters, e.g., Torque, SLURM, etc., with BatchJobs::batchMap().

For BatchJobs mode you need to define a storage directory through the argument storagedir or the option parallelMap.default.storagedir.

Value

Nothing.

parallelStop

Stops parallelization.

Description

Sets mode to "local", i.e., parallelization is turned off and all necessary stuff is cleaned up.

For socket and mpi mode parallel::stopCluster() is called.

For BatchJobs mode the subdirectory of the storagedir containing the exported objects is removed.

After a subsequent call of parallelStart(), no exported objects are present on the slaves and no libraries are loaded, i.e., you have clean R sessions on the slaves.

Usage

parallelStop()

parallelStop 13

Value

Nothing.

Index

```
BatchJobs::batchMap(), 12
                                                sapply(), 4
BatchJobs::submitJobs(), 11
                                                simpleError(), 7
batchtools::submitJobs(), 11
                                                simplify2array,6
                                                sink(), 11
character, 2, 5, 8, 11
                                                traceback(), 11
function, 4, 6
lapply(), 4
list, 6, 11
mapply(), 12
parallel::detectCores(), 11
parallel::makeCluster(), 12
parallelExport, 2
parallelExport(), 6
parallelGetOptions, 3
parallelGetRegisteredLevels, 3
parallelLapply, 4
parallelLibrary, 5
parallelLibrary(), 6
parallelMap, 6
parallelMap(), 2, 4, 5, 7-9, 11
parallelRegisterLevels, 7
parallelRegisterLevels(), 3
parallelSapply (parallelLapply), 4
parallelSource, 8
parallelSource(), 6
parallelStart, 9
parallelStart(), 2, 3, 5-8, 12
parallel Start Batch Jobs\ (parallel Start),
parallelStartBatchtools
        (parallelStart), 9
parallelStartLocal (parallelStart), 9
parallelStartMPI (parallelStart), 9
parallelStartMulticore (parallelStart),
parallelStartSocket (parallelStart), 9
parallelStop, 12
```